

Schedule Plus 5 Release Notes

SpaceLogic C-Bus

Table of Contents

Schedule Plus 5.11.0	1
Released	1
What's New	1
Installation	1
Solidworks eDrawings Viewer	1
.NET Framework 4.8.1	1
Microsoft SQL Server	2
Security Enhancements	2
Support for Latest C-Gate 3	2
Other Fixes	2
Schedule Plus 5.10.0	3
Released	3
What's New	3
Image Editor Modifications (BREAKING CHANGE)	3
User Details Dialog Modifications	3
Security Enhancements	3
Help File Updates	3
Support for Latest C-Gate 3	3
Other Fixes	3
Schedule Plus 5.9.0	4
Released	4
What's New	4
Support for Latest C-Gate 3	4
Other Fixes	4
Schedule Plus 5.8.0	5
Released	5
What's New	5
Support for Latest C-Gate 3	5
Other Fixes	5
Schedule Plus 5.7.0	6
Released	6
What's New	6

- Support for Latest C-Gate 3 6
- Other Fixes 6
- Schedule Plus 5.6.0 7
 - Released 7
 - What’s New 7
 - Support for Latest C-Gate 3 7
 - Other Fixes 7
- Schedule Plus 5.5.0 8
 - Released 8
 - What’s New 8
 - Support for Latest C-Gate 3 8
 - Other Fixes 8
- Schedule Plus 5.4.0 9
 - Released 9
 - What’s New 9
 - Support for Latest C-Gate 3 9
 - Other Fixes 9
- Schedule Plus 5.3.0 10
 - Released 10
 - What’s New 10
 - Support for Latest C-Gate 3 10
 - Other Fixes 10
- Schedule Plus 5.2.0 11
 - Released 11
 - What’s New 11
 - Support for Latest C-Gate 3 11
 - Other Fixes 11
- Schedule Plus 5.1.0 12
 - Released 12
 - What’s New 12
 - Introduction of C-Gate 3 (BREAKING CHANGE) 12
 - C-Gate Runtime 12
 - New Project Format 13
 - C-Gate 3.2.0 13
 - C-Gate Version Checking 13

- Other Fixes 14
- Schedule Plus 5.0.3 15
 - Released 15
 - What’s New..... 15
 - Removal of License Keys 15
 - Adjustments to Network Status Indicators..... 15
 - Adjustments to Network Status Detection 15
 - Adjustments to Logging 16
 - Other Fixes 16
- Schedule Plus 5.0.2 17
 - Released 17
 - What’s New..... 17
 - Image Loading 17
 - Other Fixes 17
- Schedule Plus 5.0.1 18
 - Released 18
 - What’s New..... 18
 - Dongles 18
 - Other Fixes 18
- Schedule Plus 5.0.0 19
 - Released 19
 - What’s New..... 19
 - Web Server..... 19
 - Database Logging 19
 - Database Reporting 19
 - Drawing File Support..... 19
 - Other Fixes 19

Schedule Plus 5.11.0

Released

February 2026

What's New

Installation

This release includes significant changes to how Schedule Plus is installed.

By default, Schedule Plus now installs to one of the following locations, depending on your operating system:

(32-bit Windows) C:\Program Files\Schneider Electric\Schedule Plus

(64-bit Windows) C:\Program Files (x86)\Schneider Electric\Schedule Plus

Project and template files are now respectively stored in:

Documents\Schedule Plus\Projects

Documents\Schedule Plus\Templates

⚠ Any project or template files stored in the Projects and Templates sub-folders of the existing Schedule Plus installation will be migrated by the installer to the new locations shown above as part of installing this release.

⚠ Existing files stored in the new Projects and Templates folders shown above, that have the same name as the project or template files being migrated, will be overwritten without warning.

⚠ It is **strongly recommended** that you create a backup of any existing project and template files prior to proceeding with the installation.

Once any existing data is migrated, the existing version of Schedule Plus will be uninstalled prior to the installation of this version. Moving forward, all future versions of Schedule Plus (5.11.0 and above) will also uninstall the existing version before installing themselves. User created data, such as projects, is not removed as part of this process and will remain intact. This ensures a clean starting state for Schedule Plus.

Any paths stored as an access convenience by Schedule Plus, such those in the File > Open option, will not be updated by the migration. You will need to manually browse to the new location to select the specific file when using that function, which will update the stored path.

Solidworks eDrawings Viewer

The use of Solidworks eDrawings Viewer has been obsoleted and is no longer installed with or accessible from Schedule Plus.

.NET Framework 4.8.1

Previously, parts of Schedule Plus require the .NET Framework 4 to run. Now, they require .NET Framework 4.8.1 or compatible to run.

Previously, the .NET Framework 4 Runtime was shipped with and installed as part of Schedule Plus. As of this release, the .NET Framework Runtime is no longer shipped or installed as part of the Schedule Plus installation. If you do not have it or a compatible version already installed, you will need to download and install it separately for elements of Schedule Plus to operate normally.

The installer will alert you if you do not have a compatible version of the runtime installed already.

Microsoft SQL Server

Previously, a version of Microsoft SQL Server Express was shipped with and installed by Schedule Plus as a convenience for enabling the database recording and reporting features.

As of this release, Microsoft SQL Server Express is no longer shipped or installed as part of the Schedule Plus installation.

If you wish to use the database reporting features of Schedule Plus, it is recommended that you consult with a database professional for more information on how to obtain, install, configure, secure, and connect to a Microsoft SQL Server instance to make use of the database reporting features of Schedule Plus.

⚠ *If you already have the version of Microsoft SQL Server Express that was previously shipped with Schedule Plus, and are using it, then it will continue to operate after installation of this version of Schedule Plus.*

⚠ *With the migration of the Schedule Plus projects, Microsoft SQL Server cannot access files stored in the Documents folder. Any databases stored in your project folders will need to be moved to a different location and reattached to Microsoft SQL Server using a tool like SQL Server Management Studio.*

Security Enhancements

This release includes other improvements that enhance the overall security of Schedule Plus.

Support for Latest C-Gate 3

This release adds support for connecting to version 3.7.0 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.10.0

Released

September 2025

What's New

Image Editor Modifications (BREAKING CHANGE)

This release modifies the behaviour of the *Tools > Open Image Editor* option. Now, when you invoke this option, Schedule Plus will ask the operating system to open the default image editing application it has configured. If no default editor is configured in the operating system or an error occurs while starting the default editor, then a message will be displayed informing you of this.

As a result of this change, the *Image Editor Path* option in the Program Options has also been removed.

These changes have been made to improve the security of Schedule Plus.

User Details Dialog Modifications

This release modifies the behaviour of the Access Level field in the User Details dialog. Now, the levels available to select for the new user in this field will not allow you to select a level higher than your own.

This change has been made to improve the security of Schedule Plus.

Security Enhancements

This release includes other improvements that enhance the overall security of Schedule Plus.

Help File Updates

This release includes a new topic with cybersecurity recommendations to help you improve the security of Schedule Plus. This topic can be found under *Introduction > Important Information > Cybersecurity* in the Main help file.

Support for Latest C-Gate 3

This release adds support for connecting to version 3.6.0 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.9.0

Released

June 2025

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.5.0 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.8.0

Released

February 2025

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.4.1 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.7.0

Released

October 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.4.0 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.6.0

Released

August 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.3.4 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.5.0

Released

July 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.3.3 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.4.0

Released

May 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.3.2 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.3.0

Released

April 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.3.1 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.2.0

Released

April 2024

What's New

Support for Latest C-Gate 3

This release adds support for connecting to version 3.3.0 of C-Gate 3.

Other Fixes

None.

Schedule Plus 5.1.0

Released

February 2024

What's New

Introduction of C-Gate 3 (BREAKING CHANGE)

This release requires a new version of C-Gate that is incompatible with older versions of C-Gate (2.11.11 and below) and Schedule Plus (5.0 and below).

⚠ *C-Gate 3 cannot co-exist on the same machine as C-Gate 2.*

This new version of C-Gate is required to allow configuration of new C-Bus digital dimmers and DALI devices (via a C-Bus DALI-2 Gateway) using SpaceLogic C-Bus Commission. This release of Schedule Plus allows for C-Gate 3 compatibility.


⚠ *Schedule Plus 5.1 (and above) cannot be used with C-Gate 2 (and below).*

C-Gate Runtime

This release now sees Schedule Plus automatically start and stop C-Gate locally when it is started and stopped. This is regardless of whether C-Gate is running in service or console mode locally.

If Schedule Plus is configured to connect to a remote instance of C-Gate on a different computer, then it does not attempt to start or stop C-Gate on the other computer. When connected to a local instance of C-Gate on the same computer then Schedule Plus will not attempt to stop C-Gate if there are other clients such as C-Bus Toolkit connected to it.

Automatic shutdown of C-Gate can be controlled through the Options > Program Options > C-Gate > Shut Down Behaviour setting:



New Project Format

This release adds support for the new project file format used by C-Gate 3.2.0. Only projects that have been successfully converted can be opened.


C-Gate 3.2.0

This release requires C-Gate 3.2.0 or later to operate.

⚠ *Rolling back to Schedule Plus 5.0 (and below) on a PC that has C-Bus Toolkit 1.17 (and above), and / or SpaceLogic C-Bus Commission 2 (or above), is not supported without the complete removal of C-Bus Toolkit 1.17, SpaceLogic C-Bus Commission 2 and C-Gate 3.2 first. Additionally, C-Bus projects created or updated from C-Bus Toolkit 1.17 and SpaceLogic C-Bus Commission 2 cannot be converted back to previous versions.*

C-Gate Version Checking

This release implements more stringent version checking of the C-Gate instance to which it is connected. A message is displayed if the version of C-Gate detected is not compatible with this version of Schedule Plus.



The most likely scenario where this will occur is when C-Gate has been updated as part of a SpaceLogic C-Bus Commission or C-Bus Toolkit upgrade, but Schedule Plus has not been upgraded at the same time. In this situation the Schedule Plus version will need to be updated to be compatible with the version of C-Gate that is installed.

Other Fixes

- Fixed an issue with hints displaying in the status bar of the main window when in the logic editor.
- Fixed an issue with the DALI line mapping being reset to line A when line B is selected and saved.

Schedule Plus 5.0.3

Released

April 2018

What's New

Removal of License Keys

This release removes the need for hardware license keys (dongles) during the operation of Schedule Plus. It is still required that a license appropriate to the intended use (number of networks) be purchased, but from this version onwards the hardware license is no longer required to be present during operation. Versions prior to this one still requires the license to be present, and future versions may require the hardware license to be transferred to have continued operation of Schedule Plus.

Adjustments to Network Status Indicators

This release modifies how the network status is represented in the status bar. Previously this was a text-based description that included a multi-coloured bar representation. Under normal circumstances this text could be hard to read and in certain conditions the information in it could be incorrect. The following picture illustrates the new layout of the indicators.



From left to right the indicators are:

- Online (green)
- Offline / Error (red)
- Syncing (orange)
- Operational (yellow)
- Not in Use (grey)

These indicators are only shown when Schedule Plus is connected to C-Bus. If you hover the mouse above any of the segments in the status bar, a tool tip will be displayed that indicates the meaning of that segment. It should be noted that there is no special relationship between the numbers shown. For example, if you add them together they won't necessarily equal the total number of networks in the project. Any network whose **Use in Project** flag is not set will be included in the **Not in Use** status, regardless of its actual state.

Adjustments to Network Status Detection

This release improves how Schedule Plus detects when networks are opened or closed by external means (e.g. through Toolkit, the C-Gate console, etc.). Previously, Schedule Plus could detect an external closure of a network and adjust the status accordingly, but when a network was opened externally it did not detect this scenario and the network remained in the offline state. Schedule Plus now receives notifications from C-Gate when the network interface changes state to open, puts the network into the sync state and issues a command to C-Gate to force a sync of that network. This

helps to bring the network back online within Schedule Plus as efficiently as possible. A side effect of this change is that it improves the interoperability between Schedule Plus and Toolkit.

Adjustments to Logging

Elements of the logging functionality have been improved in this release.

The **Event Log** window has been refactored to make it easier to review the log entries and the options have been consolidated onto one tab now, which should make it easier to understand the interactions between them.

Logging previously occurred within the main program thread, which meant that log entries may not have been recorded under certain situations. In this release, the logging functions now run in a separate program thread, which should improve this situation.

Log files are now named using the following convention:

SchedulePlusyyyyymmdd-n.txt

where,

- *yyyy* is the current year
- *mm* is the current month
- *dd* is the current day
- *n* is the file number for the current day

The file number starts at 1 for the current day and, if the **Limit File Size** option is enabled, will increment each time a file exceeds 10MB for the current day and a new file will be started. A new log file will automatically be started when the date rolls over.

Other Fixes

- SP-3752 – Communication issues trying to open a closed CNI network.
- SP-3756 – Incomplete opening and synchronisation of a closed C-Bus network.
- SP-3832 – Show C-Gate Messages logging option not persisted between sessions.
- SP-3833 – Page names containing \ and / cause HTML compilation to fail.
- SP-3835 – Fix webcam refresh rate being ignored.
- SP-3836 – Improve locking for objects accessed concurrently by Schedule Plus and web services.
- SP-3837 – Fix access violation in Scene Editor window.

Schedule Plus 5.0.2

Released

June 2017

What's New

Image Loading

This release modifies how images for the project are loaded. Previously all images were loaded in to memory when the project was opened. For compressed image formats, such as PNG, which are decompressed when loaded, this caused a large increase in the memory used by Schedule Plus. Images are not loaded on a just in time basis, but once loaded they remain in memory until the project is closed. This improves Schedule Plus's ability to open projects that contain many high-resolution images.

NOTE: Projects that contain many high-resolution images will still experience issues when switching to operation mode if the Web Server function is enabled. You can avoid these issues by disabling the Web Server for the project in the Project Details window.

Other Fixes

- SP-3830 – Fixed a crash when opening a project with many high-resolution images.

Schedule Plus 5.0.1

Released

January 2017

What's New

Dongles

This release removes the requirement for installer dongles to be version 5. This means that customers who have previously purchased an Installer dongle for use with earlier versions will now be able to use them with version 5.

Other Fixes

- SP-3827 – The All Profiles group does not include more than 16 profiles, regardless of how many are created.

Schedule Plus 5.0.0

Released

March 2016

What's New

Web Server

This release introduces a web server, which can optionally be enabled for a project to allow control of it via a web browser. The web server supports both unsecured HTTP and secured HTTPS connections. Access to the web server is by profiles created within the project. With a few exceptions, most Schedule Plus functionality and components can be controlled via the web server. Multiple clients connected via the web server will be synchronized, that is, if a group is turned on in one client then all the other clients will reflect that change. The web server currently supports up to 10 concurrent clients. It has been tested with all popular browsers (Chrome, Internet Explorer, Firefox, Safari, and Opera).

Database Logging

This release introduces the ability to log C-Bus events to a Microsoft SQL Server database (2008 R2 or above). The information recorded includes C-Bus project data (networks, applications, groups, levels), C-Bus application data (lighting, measurement, error reporting, HVAC, irrigation) and the Schedule Plus log. The database can also be periodically backed up and a snapshot of the Schedule Plus project recorded in the database. The installer provides an optional component that will install Microsoft SQL Server 2008 R2 Express. If you elect not to install this component, then the database functionality may still be used if you already have another instance of SQL Server installed.

Database Reporting

On top of the Database Logging functionality, this release introduces the ability to report on the information recorded in the database using Crystal Reports. This functionality is supported by a dedicated reporting window and new special functions for generating reports.

Drawing File Support

This release introduces the ability to incorporate common drawing formats such as DWG and DXF. This feature is provided by the eDrawings viewer from SolidWorks. This is an optional component when installing Schedule Plus 5, meaning that this functionality will not be available if the viewer is not installed.

Other Fixes

- SP-63 – Crash when user tries to load the projects from C-Gate and no IP address has been entered
- SP-128 – Content of HTML component not visible in operation mode
- SP-3113 – Public holiday templates updated to cover 2015-2020
- SP-3362 – Name field covering buttons in Add Irrigation Program window

- SP-3363 – Irrigation schedule not appearing when created
- SP-3364 – Add irrigation schedule wizard opening on wrong step
- SP-3407 – Memory leaks
- SP-3414 – Network status percentage displayed incorrectly when networks are offline
- SP-3443 – Added support for the C-Gate SESSION_ID TAG command
- SP-3565 – Error when entering access control pin after restoring project
- SP-3573 – Issue with appearance of version number on splash screen
- SP-3578 – General memory leaks
- SP-3579 – Web client memory leaks
- SP-3582 – Access violation with graph component
- SP-3585 – Use native OS look and feel
- SP-3589 – Select normal dongle over installer licence
- SP-3593 – Access violation when using web camera component
- SP-3594 – Memory leaks in web server
- SP-3606 – Licence check period not accurate
- SP-3625 – Maps Used field displays incorrect information in DALI window
- SP-3628 – Field layout in DALI tab of Project Details window adjusted for clarity
- SP-3630 – Increased DALI mapping limit from 512 to 1024
- SP-3631 – DALI UDP port opened exclusively
- SP-3678 – Toolkit project file prefixed with “CBus-“ when archiving
- SP-3780 – Access violation when opening an archive
- SP-3781 – Access violation related to profiles when loading a project